Free Spiril 🖉

Pocket Tote -Blue

Skill Level: Advanced Beginner/ Intermediate

Featuring: Flora by Joel Dewberry for FreeSpirit



Technique:	Sewing
Designed By:	Melissa Peda
Brand:	FreeSpirit
Crafting Time:	Afternoon

Finished Size:

10" x 4" x 12" (25.4 cm x 10.2 cm x 30.5 cm)

FreeSpirit Flora Collection by Joel Dewberry

Fabric Requirements:

(A) PWJD099.EUCAL (B) PWJD047.EUCAL (C) PWJD100.EUCAL

½ yd. (.5 m) ½ yd. (.5 m) ²/₃ yd (.61 cm)

Additional Requirements:

(1) 15" x 29" (38.1 cm x 73.7 cm) piece fusible fleece (2)11/2" x 21" (3.8 cm x 53.3 cm) strip fusible fleece (2)15" x 17" (38.1 cm x 43.2 cm) pieces Décor Bond Coats & Clark Dual Duty XP® all-purpose thread Disappearing Ink Pen or Hera Marker

> makeitcoats.com freespiritfabric.com





Pocket Tote - Blue

Notes:

Seam allowances are $1\!\!/ \!\!/ ''$ (1.3 cm) unless stated otherwise. WOF = Width Of Fabric.

Cutting Instructions:

Fabric A, cut: (2) 15" (38.1 cm) squares, for bag exterior.

Fabric B, cut:

(**2**) 15" x 17" (38.1 cm x 43.2 cm) pieces, for pockets.

Fabric C, cut:

(1) 6" x WOF (15.24 cm x WOF), for strap.(2) 15" (38.1 cm) squares, for lining

Sewing Instructions:

Bag Exterior

- Notch the top edge of each 15" (38.1) Fabric A square ¼" (.64cm).
- Right sides together, sew the squares along the bottom edge only. Press seam. Open and place right side down on work surface. Following manufacturer's instructions, fuse the 15" x 29" (38.1cm x 73.7cm) piece of fusible fleece to wrong side of fabric.
- Following manufacturer's instructions, apply a 15" x 17" (38.1cm x 43.2cm) piece of Decor Bond to the wrong side of each Fabric B pocket piece.
- Wrong sides together, fold one pocket piece so that it measures 15" x 8½" (38.1 cm x 21.6 cm). Press. Edgestitch along fold. Repeat for second pocket piece.

5. Place a folded pocket on right side of bag exterior, with raw edge 11¼" (28.6 cm) down from one top edge. Stitch in place along raw edge. Diagram 1 Flip pocket so that the folded edge is now facing toward the top. Press. Baste sides in place using a ¼" (.64 cm) seam allowance. In the same manner, sew the other pocket on the opposite side of bag exterior.

Straps

- Cut the 6" x WOF (15.24 cm x WOF) strip into two 6" x 21" (15.24 cm x 53.3 cm) strips. Fold each strip in half lengthwise and gently press a crease. Open the strips and fold each side, wrong sides together, toward the center crease. Press.
- Open each strip and place a 1½" x 21" (3.8cm x 53.3cm) piece of fusible fleece, adhesive side down, on the wrong side, using the center crease as a guide. Following manufacturer's instructions, fuse the fleece to the strips. Fold raw edges toward center.
 Diagram 2 Bring folded edges together so that each strip measures approximately 1½" (3.81cm cm) wide. Press. Edgestitch along each folded edge. Topstitch down center.
- Measure and mark 3¹/₂" (8.9 cm) away from each side seam on one side of the bag. Place outside edges of strap on marks with strap ends tucked ¹/₂" (1.3 cm) below the top edge of the pocket. Make sure there are no twists in the strap. **Diagram 3** Stitch in place using the edgestitching on the pocket as a guide. Repeat on other side of bag.

- Using a disappearing ink pen or Hera marker, mark a line from the center of one strap (where there is a stitching line) straight down the pocket. Stitch along this line. Repeat on other side of bag.
- Right sides together, sew both side seams of bag. Box stitch each of the sides 2" (5 cm) from end.
 Diagram 4

Lining

 Sew lining, right sides together, along sides and bottom, leaving a 5" (12.7 cm) opening at the bottom seam for turning. Box stitch sides 2" (5 cm) from end in the same manner as the bag's exterior.

Finishing:

- 12. Place bag inside lining, right sides together. Sew around top edge. Turn right side out through the opening in the lining and press. Slipstitch opening in lining closed.
- 13. Edgestitch along top edge of bag.
- 14. Topstitch ¼" (.64 cm) away from edgestitching.

makeitcoats.com


freespiritfabric.com



FS0284



Pocket Tote - Blue



Copyright © 2014 Coats PLC makeitcoats.com

freespiritfabric.com



FS0284

Page **3** of **3**